Account Risk Manager



PLAN WITH STRUCTURE. UNDERSTAND YOUR EXPOSURE. MANAGE WITH CONTROL.

TFP ARM brings account information, trade planning and position-management controls into an on-chart panel. This manual explains the core workflow, settings, installation and account licensing.

Inside this manual	Page
Account approval and multiple accounts	02
Install on MetaTrader 4 / MetaTrader 5	03 / 04
Licensing and access messages	05
Read the panel and prepare your settings	06
Build and review a scenario	07
Choose execution and manage positions	08
Display settings and platform differences	09
Connection and daily checks	10
Troubleshooting and support	11
Responsible use and final checklist	12

ACCESS IS SEPARATE FROM TRADING READINESS

TFP access: Active means your licence is valid. ARM's own READY or BLOCKED message describes its separate trading and risk checks. READY is not a trade signal or a guarantee of an accepted order.

Your account & EA access

MEMBER MANUAL / MT4 + MT5



Access is linked to your approved trading account, platform and EA. Your website login and your MetaTrader trading account are separate.

1 Register or sign in

Create your TFP member login and confirm your email. Use the Broker partners page for the current XM registration instructions.

2 Use an eligible real XM account

For a new XM registration, use the TFP partner link and code shown on the website. If you already have XM access, follow the existing-client instructions to open an additional trading account under the TFP partner arrangement. An existing account is not automatically linked.

3 Submit the account for approval

Enter your XM trading account number linked to our Trading Final Piece partner code. We will check the account before approving access. Select MT4 or MT5 correctly; never submit your trading password.

4 Download for that account

Once approved, choose the account and EA in Downloads. You can register more than one eligible account under one member login; each needs its own approval and matching installation.

CURRENT ACCESS RULES

This release supports approved real XM accounts. Demo accounts and other brokers are not supported. ARM and Edge have separate access records for each account.

Install on MetaTrader 4

MEMBER MANUAL / MT4 + MT5



1 Download and extract your personal ZIP

In the member area, select the approved MT4 account and this EA. Extract the download and open INSTALL.txt.

2 Open the correct terminal data folder

In MetaTrader, select File > Open Data Folder. Keep the folder open, then close MetaTrader. Back up an existing installation before replacing files.

3 Copy the complete MQL4 folder

Copy the extracted MQL4 folder into the data folder and merge it with the existing folder. Include Experts and Files. Experts contains the .ex4 EA; Files contains your account installation data.

4 Reopen MetaTrader and allow the connection

Open Tools > Options > Expert Advisors. Enable Allow WebRequest for listed URL. Add the exact address printed in your download's INSTALL.txt, then click OK.

5 Attach and check

Log in to the account selected for the download. Refresh Expert Advisors in Navigator and attach the EA to a chart. Wait for TFP access: Active, then review the EA settings and platform trading permissions separately.

YOUR LICENCE IS ALREADY INCLUDED

There is no licence token to type into Inputs. Copying only the .ex4 file is not enough. Keep the personalised ZIP and licence files private.

Install on MetaTrader 5

MEMBER MANUAL / MT4 + MT5



1 Download and extract your personal ZIP

In the member area, select the approved MT5 account and this EA. Extract the download and open INSTALL.txt.

2 Open the correct terminal data folder

In MetaTrader, select File > Open Data Folder. Keep the folder open, then close MetaTrader. Back up an existing installation before replacing files.

3 Copy the complete MQL5 folder

Copy the extracted MQL5 folder into the data folder and merge it with the existing folder. Include Experts and Files. Experts contains the .ex5 EA; Files contains your account installation data.

4 Reopen MetaTrader and allow the connection

Open Tools > Options > Expert Advisors. Enable Allow WebRequest for listed URL. Add the exact address printed in your download's INSTALL.txt, then click OK.

5 Attach and check

Log in to the account selected for the download. Refresh Expert Advisors in Navigator and attach the EA to a chart. Wait for TFP access: Active, then review the EA settings and platform trading permissions separately.

YOUR LICENCE IS ALREADY INCLUDED

There is no licence token to type into Inputs. Copying only the .ex5 file is not enough. ARM MT5 requires a hedging account; netting accounts are not supported.

How your licence works

MEMBER MANUAL / MT4 + MT5



Download, install, connect

Your personal download contains the account licence. The EA checks the account, broker, platform and product automatically, then renews access through the allowed website connection. You do not enter a licence key or run a separate licence helper. The connection also reports EA activity to the TFP administrator for access and support purposes.

What you see	What it means
TFP access: Active	The account licence is valid. Trading permissions, market conditions and the EA's own rules still apply.
Account not authorised	Check that you installed the complete personal download and logged in to its approved account.
Invalid broker / demo account	Use the approved real XM account. Changing Inputs does not bypass this restriction.
Account access inactive	Check approval and licence status in the member area. A paused licence must be resumed by the administrator.
Verifying / verification expired	Check the allowed URL, internet connection and computer date/time. Read the Experts log for the exact message.

If access is paused or the connection is lost

ARM blocks new entries through its integrated licence checks when valid access is unavailable. Existing position-management routines can continue. Pausing a licence does not close open positions or switch off all EA behaviour.

> **ACCESS CHANGES ARE NOT INSTANT**
>
> A currently valid permission can remain usable for up to 15 minutes. Keep MetaTrader connected. Check the member area and the EA access label; do not use licence pause as an emergency trade-close control.

Read the panel & review settings



MEMBER MANUAL / MT4 + MT5

Normal trading and risk controls are managed from the on-chart panel. EA Inputs supply startup defaults; saved panel and scenario values can also affect what you see. Review the live panel each time you load ARM.

Area	What to review
Account	Account identity, balance/equity, existing exposure and available margin.
Signal / scenario	Selected symbol and direction; entry, stop and target distances; risk mode and planned stack.
Active Trades	Actual open positions and the scope of each management control.
Protection	Drawdown, margin usage, margin-call/stop-out buffers and positions without a stop loss.
Status	Read the specific reason for BLOCKED before considering an entry.

Starting behaviour

The supplied MT4 and MT5 builds start with DefaultExecutionMode = 0 (Planning) and AllowAutoExecution = false. Check the current panel mode rather than assuming the startup setting is still in effect.

> **PLANNING STILL HAS LIVE CONTROLS**
>
> Planning disables automatic scenario execution. Row trade buttons can still place real orders when platform trading is enabled and the checks pass. Planning is not a simulation account.

The included numerical risk defaults are software starting values, not recommended limits for every account. Review each risk and protection setting before live use.

Build a scenario from your trade plan

MEMBER MANUAL / MT4 + MT5



1 Select the symbol and direction

Use the broker's exact symbol. Confirm Buy or Sell and review its contract size, tick value, volume step and trading hours.

2 Enter the plan

Enter the planned entry, stop-loss and take-profit distances and the applicable risk and stack settings. Use the units displayed by the panel.

3 Choose and review the risk mode

Normal and Global risk modes use different planning logic. Review the selected mode, the account risk already in use and any common basket levels shown. Do not switch modes without recalculating.

4 Calculate

Use Calculate. Inspect every planned entry, lot size, stop, target and estimated margin/exposure. Check that the plan matches your intended maximum cash risk.

5 Approve deliberately

Review the scenario before using USE SCENARIO or a live trade control. An approved plan is still subject to current price, licence, protection and broker checks.

> **RECALCULATE AFTER CHANGING THE PLAN**
>
> Changes to scenario inputs invalidate the earlier calculation. Recalculate and review again. Planned levels and projected results are estimates; actual fills can differ.

Execution modes & active trades

MEMBER MANUAL / MT4 + MT5



Mode	Behaviour
0 - Planning	Automatic execution is off. Live row trade buttons remain available subject to checks.
1 - Assisted	ARM monitors and alerts; you decide whether to execute.
2 - Auto	Approved-scenario execution requires AllowAutoExecution and platform trading permissions. Understand the scenario before enabling it.

Review the positions ARM can affect

ARM includes account-wide information and controls. Some protection or close actions can affect positions beyond the current chart or ARM's own trades. Read the scope of the action before you use it.

Manage with a clear intention

Use Active Trades to review actual positions. Before modifying a stop, taking a partial close or closing a position, verify the selected trade, volume and action. Check the broker response and the resulting position afterwards.

Close All and other broad actions

Follow the confirmation shown by your installed release. In the supplied MT4 build, Close All needs a second click within five seconds. Never use a broad action as if it only affects a single chart trade.

> **DO NOT USE LICENCE PAUSE TO CLOSE TRADES**
>
> A paused licence blocks new entries once invalid access is detected; existing management may continue. It does not automatically close positions. Use the appropriate trading controls and verify the result.

Panel display & platform differences

MEMBER MANUAL / MT4 + MT5



Input	Purpose
PanelScalePercent	Changes the complete panel size. Supplied default: 100; supported range: 35-125.
PanelAutoFit	Can shrink the panel further to fit the chart. Default: false.
PanelAllowDrag	Allows dragging by the header. Default: true.
RememberPanelPosition	Remembers the panel position. Default: true.
ResetSavedPanelPosition	Set true once to restore the starting position, then return it to false.
PanelStartX / PanelStartY	Starting position used when resetting the panel.

MT5 requires a hedging account

The supplied ARM MT5 build rejects netting and exchange account modes. A hedging account supports separate positions on the same symbol. Check the account type before installing.

Rebuild scenarios when changing platforms

MT4 saved scenarios are not imported into MT5. Recreate and review the plan in MT5, including symbols, contract specifications, volumes, stops and targets. Use the correct personal licence download for each account and platform.

> **DISPLAY CHANGES DO NOT CHANGE YOUR LICENCE**
>
> Panel size and position are display preferences. They do not approve an account or remove a trading block. Use the access label and the panel status for those checks.

Connection & daily checks

MEMBER MANUAL / MT4 + MT5



Which website address should I add?

Use https://tradingfinalpiece.com exactly as shown in INSTALL.txt. This is the live Trading Final Piece WebRequest address. Do not use an address copied from an older guide or installation.

> **DO NOT ENTER A TOKEN**
>
> Older instructions referring to TFP_LicenseToken do not apply to this integrated release. The complete download supplies the licence automatically.

If support asks you to change the address

Download a fresh personal installation for the same approved account, copy the complete package and allow the address in its new INSTALL.txt. Follow any release-update instructions shown in the member area. The connection change does not itself require different trading settings.

Before each session

Check	Confirm
Account	Correct real account, broker and MT4/MT5 platform.
Access	Top-right TFP access label shows Active.
Settings	Correct symbol, chart, mode, lot size and risk controls.
Permissions	AutoTrading / Algo Trading and EA permissions match your intended actions.
Positions	You understand which existing trades the EA may manage.
Connection	MetaTrader is online; the correct URL remains allowed.

A browser message such as POST required is not a licence test. Check the EA access label inside MetaTrader.

Troubleshooting & support

MEMBER MANUAL / MT4 + MT5



The EA is missing from Navigator

Check this terminal's data folder. MT4 uses .ex4; MT5 uses .ex5. Refresh Expert Advisors or restart the terminal.

The licence is missing or not valid

Install the complete personal package, including Files. Match the logged-in account to the account selected for the download.

Access is Active, but no trade opens

Active confirms licensing only. Check platform permissions, scenario approval, execution mode, risk and protection limits, market hours and broker order restrictions.

The connection cannot be verified

Check WebRequest, the exact INSTALL.txt address, internet and computer time. Copy the exact Experts log message for support.

I changed account or platform

Add and obtain approval for the new account, then download its matching package. Do not rename or reuse another account's licence.

> **SUPPORT IS IN YOUR MEMBER AREA**
>
> Open a Support ticket and include the EA name, MT4 or MT5, release version, what you did and the exact error. Replies appear on the website. Never attach your passwords, personalised ZIP or licence file.

Use the tools with care

MEMBER MANUAL / MT4 + MT5



Understand the controls before live use

These are software instructions, not a promise of trading results. Trading involves risk of loss. Market gaps, price movement, broker restrictions, slippage and connection or software interruptions can affect orders and protection.

Settings are not a guarantee

A stop loss, drawdown limit or account-protection setting does not guarantee a maximum loss. Actual fills may differ from planned prices. Monitor the account and check that submitted stops and targets are present and correct.

Start with installation checks

For an initial connection-only check, leave platform automated trading off and use an account with no positions requiring EA management. Confirm access and review the settings. This does not validate order execution. The licensed member build does not provide demo-account access.

Keep your installation private

Use your personal package only for its approved account and platform. Do not share, sell or redistribute the ZIP or licence files. Add further eligible accounts through your member area.

> **YOUR SESSION CHECKLIST**
>
> Correct account. Valid access. Reviewed settings. Clear execution mode. Understood position scope. Working connection. Check each item before allowing the EA to act.

Need help? Open a ticket in the member area before changing unfamiliar settings.